

# HarvestLab™ Software Update V145 Release Notes

## Important Notes:

This software is updating your HarvestLab™ 3000 sensor to version V145.

To perform the software update, please download the software bundle from StellarSupport™ at HarvestLab™ section. To connect the HarvestLab™ 3000 sensor with your laptop, you must use an Ethernet cable (PFP16262: Ethernet Cable (M12 to RJ45)). Please follow the steps on HarvestLab™ web UI to update the software.

(<https://www.youtube.com/watch?v=atQQGueHYJY&feature=youtu.be>)

## Release Notes:

Date	Software	Version
November 2022	John Deere Harvestlab™ 3000 sensor	V145

### V145

New Feature - Added support for changing the constituent unit between % and g/kg.

New Feature - Display remaining warmup time in calibration dialog.

Enhancement - Improved the handling of demo calibrations – demo of new calibration bundles can be tested even if an older calibration bundle is activated

Enhancement - Improved time synchronization between display and HarvestLab.

Enhancement - Added sample name to downloaded spectra.

Enhancement - Added sample number and sensor serial number to PDF and CSV measurement reports.

Enhancement - Improved window cleanliness check handling.

Enhancement - Changed moisture base for grain in various regions.

Bug – Fixes

**Note: A refresh of the browser is needed after installation of software update.**